

# IkeaDocuScan V3 - Deployment Plan

**Target Environment:** Windows Server with IIS and SQL Server **Framework:** .NET 10.0  
**Application Type:** ASP.NET Core with Blazor WebAssembly **Organization:** IKEA  
(ikea.com)

---

## Table of Contents

1. [Prerequisites](#)
  2. [Pre-Deployment Checklist](#)
  3. [Version Management](#)
  4. [Publishing from Visual Studio](#)
  5. [Database Setup](#)
  6. [IIS Configuration](#)
  7. [Application Configuration](#)
  8. [File Permissions](#)
  9. [Windows Authentication Setup](#)
  10. [Post-Deployment Verification](#)
- 

## Prerequisites

### Server Requirements

- Windows Server 2019 or later
- IIS 10.0 or later with ASP.NET Core Hosting Bundle
- SQL Server 2017 or later
- .NET 10.0 Runtime and Hosting Bundle installed

### Required IIS Features

- Windows Authentication
- Application Development → ASP.NET 4.x (for compatibility)
- Application Development → WebSocket Protocol (for SignalR)
- Security → Request Filtering

### Required Software on Deployment Machine

- Visual Studio 2022 (v17.8 or later)
- SQL Server Management Studio (SSMS)
- Access to target server (RDP or file share)

### Access Requirements

- SQL Server sysadmin or db\_owner role
  - IIS Administrator permissions
  - File system write permissions on deployment directory
  - Active Directory read access (for Windows Authentication)
- 

## Pre-Deployment Checklist

- ☐ Backup current production database (if upgrading)
- ☐ Backup current appsettings.Local.json (if exists)

- ☐ Backup current secrets.encrypted.json (if exists)
  - ☐ Document current version number
  - ☐ Verify .NET 10.0 Runtime installed on target server
  - ☐ Verify ASP.NET Core Hosting Bundle 10.0 installed
  - ☐ Schedule maintenance window (if required)
  - ☐ Notify users of deployment (if downtime expected)
- 

## Version Management

### Understanding the Version System

The application uses .NET's built-in versioning with two components:

**In IkeaDocuScan-Web.csproj:**

```
<VersionPrefix>3.0.*</VersionPrefix>
<VersionSuffix>beta.10Nov25</VersionSuffix>
```

**Version Format:** {VersionPrefix}.{Auto-Build}.{Auto-Revision}-{VersionSuffix} **Example:** 3.0.1234.5678-beta.10Nov25

### Setting the Version for Release

**Step 1:** Open IkeaDocuScan-Web.csproj in Visual Studio

**Step 2:** Update version properties:

```
<!-- For Production Release -->
<VersionPrefix>3.1.0</VersionPrefix>
<VersionSuffix></VersionSuffix>

<!-- For Beta/RC Release -->
<VersionPrefix>3.1.0</VersionPrefix>
<VersionSuffix>rc1</VersionSuffix>

<!-- For Hotfix -->
<VersionPrefix>3.0.1</VersionPrefix>
<VersionSuffix></VersionSuffix>
```

**Step 3:** Save the file

**Step 4:** Rebuild solution to apply new version

**Version Visibility:** The version is displayed in: - Assembly metadata - Application logs - Can be added to UI footer (future enhancement)

---

## Publishing from Visual Studio

### Step 1: Clean and Rebuild Solution

1. In Visual Studio, right-click the Solution in Solution Explorer
2. Select **Clean Solution**
3. Wait for completion
4. Right-click the Solution again
5. Select **Rebuild Solution**
6. Verify no build errors in Output window

### Step 2: Publish the Application

1. Right-click **IkeaDocuScan-Web** project (not the solution)
2. Select **Publish...**

### Step 3: Create or Select Publish Profile

**For First-Time Deployment:** 1. Click **New** to create a new publish profile 2. Select **Folder** as target 3. Click **Next** 4. Choose folder location (e.g., C:\Publish\IkeaDocuScan) 5. Click **Finish** 6. Profile will be saved in Properties\PublishProfiles\

**For Subsequent Deployments:** 1. Select existing publish profile from dropdown 2. Click **Show all settings** to verify configuration

### Step 4: Configure Publish Settings

Click **Show all settings** and verify:

Setting	Value
Configuration	Release
Target Framework	net9.0
Deployment Mode	Framework-dependent
Target Runtime	Portable
File Publish Options	<input checked="" type="checkbox"/> Delete existing files prior to publish
	<input checked="" type="checkbox"/> Exclude files from App_Data folder

**Important:** Use **Framework-dependent** deployment (not self-contained) to reduce publish size and rely on server's .NET runtime.

### Step 5: Publish

1. Click **Publish** button
2. Monitor Output window for progress
3. Verify success message: "Publish succeeded"
4. Note the publish folder path

### Step 6: Verify Published Files

Navigate to publish folder and verify these key files exist:

```
IkeaDocuScan-Web.dll
IkeaDocuScan-Web.deps.json
IkeaDocuScan-Web.runtimeconfig.json
appsettings.json
appsettings.Production.json
web.config
wwwroot/
  _framework/
```

**Do NOT copy these files to server (will be created manually):** -  
appsettings.Local.json - secrets.encrypted.json

### Step 7: Include Database Migration Scripts

**IMPORTANT:** The database migration scripts must be included in the deployment package.

1. Navigate to solution root directory: IkeaDocuScanV3\
2. Verify the DbMigration\db-scripts\ folder exists and contains all SQL scripts
3. Copy the entire folder to the publish directory:

```
xcopy /E /I "DbMigration\db-scripts" "C:\Publish\IkeaDocuScan\DbMigrati
```

#### 4. Verify ALL SQL scripts are present in the correct order:

The scripts must be executed in this exact sequence:

```
DbMigration\db-scripts\
├── 00_Create_Database_And_User.sql
├── 00A_Restore_And_Migrate_Schema.sql
├── 02_Migrate_FK_Data.sql
├── 03_Finalize_FK_Constraints.sql
├── 04_Create_DocuScanUser_Table.sql
├── 05_Migrate_Users_To_DocuScanUser.sql
├── 06_Add_FK_Constraint_UserPermissions.sql
└── 07_Remove_AccountName_From_UserPermissions.sql
```

#### 5. Create a checklist to verify all scripts are present:

```
[ ] Script 1: 00_Create_Database_And_User.sql
[ ] Script 2: 00A_Restore_And_Migrate_Schema.sql
[ ] Script 4: 02_Migrate_FK_Data.sql
[ ] Script 5: 03_Finalize_FK_Constraints.sql
[ ] Script 6: 04_Create_DocuScanUser_Table.sql
[ ] Script 7: 05_Migrate_Users_To_DocuScanUser.sql
[ ] Script 8: 06_Add_FK_Constraint_UserPermissions.sql
[ ] Script 9: 07_Remove_AccountName_From_UserPermissions.sql
```

**Action Required Before Deployment:** - Deployer must verify all 8 scripts are present before creating deployment ZIP

**These scripts will be executed manually in SQL Server Management Studio during database setup.**

### Step 8: Copy ConfigEncryptionTool

#### 1. Navigate to ConfigEncryptionTool publish output:

```
cd ConfigEncryptionTool\bin\Release\net10.0
```

#### 2. Copy ConfigEncryptionTool.exe and dependencies to deployment package:

```
xcopy /E /I ConfigEncryptionTool.exe "C:\Publish\IkeaDocuScan\Tools\ConfigEncryptionTool\Con
xcopy /E /I *.dll "C:\Publish\IkeaDocuScan\Tools\ConfigEncryptionTool\Con
```

### Step 9: Create Deployment ZIP File

#### 1. Navigate to publish folder parent directory:

```
cd C:\Publish
```

#### 2. Create ZIP file with timestamp:

```
$timestamp = Get-Date -Format "yyyyMMdd_HH:mm:ss"
$zipName = "IkeaDocuScan_v3_$timestamp.zip"
Compress-Archive -Path "IkeaDocuScan\*" -DestinationPath $zipName
```

#### 3. Verify ZIP file contents:

- Application DLLs and files
- DbMigration-scripts\*.sql
- Tools\*

#### 4. Transfer ZIP file to target server using approved file transfer method

## Database Setup

**IMPORTANT:** The production database will contain existing data from the current production system. The database upgrade is performed through SQL migration scripts, **NOT** Entity Framework migrations.

## Step 1: Restore Production Database Backup

### For Production/Dev/Test Deployment:

1. Obtain the latest backup of the current production IkeaDocuScan database (for dev/test could be an export that excludes tables Document and DocumentFile)
2. Open SQL Server Management Studio (SSMS)
3. Connect to the production SQL Server instance
4. Run the 8 dll scripts in DbMigration-scripts

## Step 2: Execute Database Migration Scripts

**CRITICAL:** The migration scripts must be executed in the exact order specified below using SQL Server Management Studio.

**DO NOT USE Entity Framework Migrations** - This deployment uses custom SQL scripts only.

**Script Location:** C:\inetpub\wwwroot\IkeaDocuScan\DbMigration\db-scripts\  
(extracted from deployment ZIP)

### Execution Order:

The scripts are prefixed with numbers to indicate execution order. Execute ALL 8 scripts sequentially:

Order	Script Name	Purpose
1	00_Create_Database_And_User.sql	Creates database and application user
2	00A_Restore_And_Migrate_Schema.sql	Restores schema from backup
3	02_Migrate_FK_Data.sql	Migrates data for foreign keys
4	03_Finalize_FK_Constraints.sql	Creates foreign key constraints
5	04_Create_DocuScanUser_Table.sql	Creates DocuScanUser table
6	05_Migrate_Users_To_DocuScanUser.sql	Migrates user data
7	06_Add_FK_Constraint_UserPermissions.sql	Adds FK to UserPermissions
8	07_Remove_AccountName_From_UserPermissions.sql	Removes obsolete column

### Execution Steps:

1. Open SQL Server Management Studio (SSMS)
2. Connect to SQL Server instance
3. Ensure connected to **IkeaDocuScan** database (dropdown at top)
4. Navigate to script folder: C:\inetpub\wwwroot\IkeaDocuScan\DbMigration\db-scripts\  
**5. Execute each script in order (1-8 as listed in table above):**

**For each script:**

- a. Click **File** → **Open** → **File**
- b. Select the script file (in correct order)
- c. **Verify** database dropdown shows: **IkeaDocuScan**
- d. **Review** script contents briefly (do NOT modify)
- e. Click **Execute** (F5) or press F5
- f. **Wait** for completion - watch Messages tab
- g. **Verify** success message: “Command(s) completed successfully”
- h. **Check** Messages tab for:
  - Row counts affected
  - Any warnings (yellow)
  - Any errors (red - STOP if errors occur)
- i. **Document** completion:
 

```
Script: [name]
Execution Time: [duration]
Rows Affected: [count]
Warnings: [none/list]
Status: SUCCESS / FAILED
```
- j. If **SUCCESS**, proceed to next script
- k. If **FAILED**, STOP and contact development team immediately

6. **After ALL scripts complete successfully:**

**Verify database state:**

```
-- Verify migration completed
SELECT @@SERVERNAME AS ServerName,
       DB_NAME() AS DatabaseName,
       GETDATE() AS MigrationCompletedAt;

-- Check table count
SELECT COUNT(*) AS TableCount
FROM INFORMATION_SCHEMA.TABLES
WHERE TABLE_TYPE = 'BASE TABLE';

-- Sample data check
SELECT COUNT(*) AS DocumentCount FROM Document;
SELECT COUNT(*) AS DocumentTypeCount FROM DocumentType;
SELECT COUNT(*) AS UserCount FROM DocuScanUser;
```

Expected results (approximate - actual counts may vary):

- TableCount: 10-15 tables
- DocumentCount: [varies based on production data]
- DocumentTypeCount: 5-20 types
- UserCount: [varies based on production data]

**Important Notes:**

- ☐ **Do NOT skip any scripts**
- ☐ **Do NOT change the execution order**
- ☐ **Do NOT modify script contents**
- ☐ **Execute ONE script at a time**
- ☐ If a script fails:
  - Note the exact error message
  - Note which script failed
  - Note how far through the script execution progressed
  - STOP immediately - do NOT continue

- Contact development team with error details
- ☐ Keep a detailed log of:
  - Each script name
  - Execution start/end time
  - Rows affected
  - Any warnings or messages
  - Final status (SUCCESS/FAILED)

### Script Execution Log Template:

Database Migration Execution Log

Date: \_\_\_\_\_

Database Server: \_\_\_\_\_

Database Name: IkeaDocuScan

Executed By: \_\_\_\_\_

Script Execution Details:

-----

Script 1: 00\_Create\_Database\_And\_User.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 2: 00A\_Restore\_And\_Migrate\_Schema.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 3: 02\_Migrate\_FK\_Data.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 4: 03\_Finalize\_FK\_Constraints.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 5: 04\_Create\_DocuScanUser\_Table.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 6: 05\_Migrate\_Users\_To\_DocuScanUser.sql

Start Time: \_\_\_\_\_

End Time: \_\_\_\_\_

Duration: \_\_\_\_\_

Rows Affected: \_\_\_\_\_

Warnings: \_\_\_\_\_

Status: [ ] SUCCESS [ ] FAILED

Notes: \_\_\_\_\_

Script 7: 06\_Add\_FK\_Constraint\_UserPermissions.sql  
Start Time: \_\_\_\_\_  
End Time: \_\_\_\_\_  
Duration: \_\_\_\_\_  
Rows Affected: \_\_\_\_\_  
Warnings: \_\_\_\_\_  
Status: [ ] SUCCESS [ ] FAILED  
Notes: \_\_\_\_\_

Script 8: 07\_Remove\_AccountName\_From\_UserPermissions.sql  
Start Time: \_\_\_\_\_  
End Time: \_\_\_\_\_  
Duration: \_\_\_\_\_  
Rows Affected: \_\_\_\_\_  
Warnings: \_\_\_\_\_  
Status: [ ] SUCCESS [ ] FAILED  
Notes: \_\_\_\_\_

OVERALL STATUS: [ ] ALL SCRIPTS SUCCESSFUL [ ] MIGRATION FAILED

Signature: \_\_\_\_\_ Date: \_\_\_\_\_

### Step 3: Verify Database User (Created by Scripts)

The migration scripts automatically create the application database user.

#### Verify the user was created:

```
USE IkeaDocuScan;
GO

-- Check if Login exists
SELECT name, type_desc, create_date
FROM sys.server_principals
WHERE name = 'docuscanch';

-- Check if database user exists
SELECT name, type_desc, create_date
FROM sys.database_principals
WHERE name = 'docuscanch';

-- Verify user permissions
EXEC sp_helpuser 'docuscanch';
```

**Expected Result:** - Login docuscanch exists at server level - User docuscanch exists in IkeaDocuScan database - User has db\_datareader, db\_datawriter roles

#### If user was NOT created by scripts:

Contact development team immediately. The migration scripts should handle user creation.

### Step 4: Test Database Connection

Test connectivity with the application user:

```
-- Test as docuscanch user
EXECUTE AS USER = 'docuscanch';

-- Should succeed (read access)
SELECT COUNT(*) FROM Document;
SELECT COUNT(*) FROM DocumentType;

-- Revert to admin
REVERT;
```

**Expected:** Queries execute successfully without errors.

### Step 5: Verify Database Configuration Tables



**To Be Defined:** Some application configuration settings are stored in database tables. The exact tables and initial configuration will be documented by the development team.

**Placeholder for configuration verification:**

```
-- Configuration tables to be verified
-- TODO: Add specific tables and validation queries
-- Example: SELECT * FROM SystemConfiguration;
```

**Action Required:** Development team to provide: - List of configuration tables - Required configuration records - Validation queries - Seed data scripts (if needed)

---

## IIS Configuration

### Step 1: Extract Deployment Package

1. Copy the deployment ZIP file to the server (e.g., C:\Temp\)
2. Extract ZIP file to deployment directory:

```
Expand-Archive -Path "C:\Temp\IkeaDocuScan_v3_*.zip" -DestinationPath "
```

**OR** using Windows Explorer:

- Right-click ZIP file → **Extract All**
- Target: C:\inetpub\wwwroot\IkeaDocuScan

3. Verify extracted contents:

```
C:\inetpub\wwwroot\IkeaDocuScan\
├── IkeaDocuScan-Web.dll
├── web.config
├── wwwroot\
├── DbMigration\
│   └── db-scripts\
├── Tools\
│   └── ConfigEncryptionTool\
```

### Step 2: Create Application Pool

1. Open IIS Manager
2. Expand server node
3. Right-click **Application Pools** → **Add Application Pool**

Setting	Value
Name	IkeaDocuScan
.NET CLR version	No Managed Code
Managed pipeline mode	Integrated
Start application pool immediately	<input checked="" type="checkbox"/>

4. Click **OK**

### Step 3: Configure Application Pool

1. Select **IkeaDocuScan** application pool
2. Click **Advanced Settings** in right panel

Setting	Value	Notes
General → .NET CLR Version	No Managed Code	Required for .NET Core
General → Managed Pipeline Mode	Integrated	
General → Start Mode	AlwaysRunning	Faster startup
Process Model → Identity	ApplicationPoolIdentity	Most secure option
Process Model → Idle Time-out (minutes)	0	Disable idle timeout
Process Model → Load User Profile	True	Required for DPAPI encryption
Recycling → Regular Time Interval	1740 (29 hours)	Avoid daily recycling

3. Click **OK**

**Important:** If using Windows Authentication with Active Directory, you may need to use a domain service account instead of ApplicationPoolIdentity because the account must be known to the domain: - Identity: **Custom Account** → DOMAIN\ServiceAccount

## Step 4: Create IIS Website

### Option A: Create New Website

1. Right-click **Sites** → **Add Website**

Setting	Value
Site name	IkeaDocuScan
Application pool	IkeaDocuScan
Physical path	C:
Binding → Type	https
Binding → IP address	All Unassigned
Binding → Port	443
Binding → Host name	docuscan.company.com
Binding → SSL certificate	(Select appropriate certificate)

2. Click **OK**

### Option B: Create as Application under Existing Site

- Expand **Sites** → **Default Web Site**
- Right-click **Default Web Site** → **Add Application**

Setting	Value
Alias	docuscan
Application pool	IkeaDocuScan
Physical path	C:

3. Click **OK**

## Step 5: Configure Website Settings

- Select the IkeaDocuScan site/application
- Double-click **Authentication**

Authentication Type	Status
Anonymous Authentication	Disabled
Windows Authentication	<b>Enabled</b>

3. Click **Windows Authentication** → **Advanced Settings**
  - Extended Protection: **Accept**
  - Enable Kernel-mode authentication: ☒

## Step 6: Configure Application Settings

1. Select IkeaDocuScan site/application
2. Click **Configuration Editor** in main panel
3. Select **system.webServer/aspNetCore** section
4. Verify settings:

Setting	Value
processPath	dotnet
arguments	.- Web.dll
stdoutLogEnabled	true
stdoutLogFile	.
hostingModel	inprocess

5. Click **Apply**

## Step 7: Configure WebSocket Protocol (for SignalR)

1. Select IkeaDocuScan site/application
2. Double-click **WebSocket Protocol** feature
3. If not installed:
  - Open **Server Manager**
  - **Manage** → **Add Roles and Features**
  - Navigate to **Web Server (IIS)** → **Web Server** → **Application Development**
  - Check **WebSocket Protocol**
  - Install

---

## Application Configuration

### Step 1: Use ConfigEncryptionTool to Create Encrypted Configuration

**IMPORTANT:** The connection string must be encrypted using Windows DPAPI. Use the provided ConfigEncryptionTool.

**Why Encrypt:** The database connection string contains the docuscanch user password and should not be stored in plain text.

#### Running the Tool:

1. Navigate to the tools directory:

```
cd C:\inetpub\wwwroot\IkeaDocuScan\Tools\ConfigEncryptionTool
```

2. Run as the IIS Application Pool identity:

```
runas /user:"IIS APPPOOL\IkeaDocuScan" "cmd.exe"
```

3. In the new command prompt window:

```
cd C:\inetpub\wwwroot\IkeaDocuScan\Tools\ConfigEncryptionTool
ConfigEncryptionTool.exe
```

4. Follow the interactive prompts:

```
DATABASE CONFIGURATION:
SQL Server: [Enter SQL Server name, e.g., PROD-SQL-01]
Database Name: IkeaDocuScan
Use Windows Authentication? n
Username: docuscanch
Password: [Enter docuscanch password - characters will be masked]
```

```
APPLICATION CONFIGURATION:
Scanned Files Path: \\fileserver\ScannedDocuments
```

5. Tool will create secrets.encrypted.json with encrypted connection string
6. Verify encryption test succeeds
7. Copy secrets.encrypted.json to application root:

```
copy secrets.encrypted.json C:\inetpub\wwwroot\IkeaDocuScan\
```

#### Output File Format:

```
{
  "ConnectionStrings": {
    "DefaultConnection": "[ENCRYPTED_VALUE_USING_DPAPI]"
  },
  "IkeaDocuScan": {
    "ScannedFilePath": "\\fileserver\ScannedDocuments"
  }
}
```

**Security Notes:** - The encrypted file can ONLY be decrypted on this machine with the same user account - Backup this file as part of server backups - Do NOT commit to source control

#### Step 2: Create appsettings.Local.json

Create appsettings.Local.json in C:\inetpub\wwwroot\IkeaDocuScan\ with IKEA-specific settings:

```

{
  "IkeaDocuScan": {
    "ContactEmail": "docuscan-support@ikea.com",

    "DomainName": "ikea.com",

    "UserEmail": {
      "LDAPRoot": "LDAP://DC=ikea,DC=com",
      "LDAPFilter": "(sAMAccountName={0})"
    },

    "EmailGroups": {
      "LDAPRoot": "LDAP://OU=Ikea,OU=Collab,DC=ikea,DC=com",
      "LDAPFilter": "(name=*Reminder*)"
    },

    "ADGroupReader": "IKEA\\UG-DocScanningReaders-CG@WAL-FIN-CH-GEL",
    "ADGroupPublisher": "IKEA\\UG-DocScanningPublishers-CG@WAL-FIN-CH-GEL"
    "ADGroupSuperUser": "IKEA\\UG-DocScanningSuperUsers-CG@WAL-FIN-CH-GEL"
  },

  "Email": {
    "SmtpHost": "smtp-gw.ikea.com",
    "SmtpPort": 25,
    "UseSsl": false,
    "SmtpUsername": "",
    "SmtpPassword": "",
    "FromAddress": "noreply-docuscan@ikea.com",
    "FromDisplayName": "IKEA DocuScan System",
    "AdminEmail": "docuscan-admins@ikea.com",
    "ApplicationUrl": "https://docuscan.ikea.com"
  },

  "ExcelExport": {
    "ApplicationUrl": "https://docuscan.ikea.com"
  },

  "Logging": {
    "LogLevel": {
      "Default": "Information",
      "Microsoft.AspNetCore": "Warning",
      "Microsoft.EntityFrameworkCore": "Warning"
    }
  }
}

```

**Configuration Priority (highest to lowest):** 1. Environment Variables (IIS App Pool) 2. secrets.encrypted.json ← **Connection string (encrypted)** 3. appsettings.Local.json ← **Server-specific settings** 4. appsettings.Production.json ← **Deployed with app** 5. appsettings.json ← **Deployed with app (defaults)**

**Configuration Sections Explained:**

Section	Purpose	Notes
DomainName	IKEA Active Directory domain	Used for user authentication
UserEmail.LDAPRoot	LDAP path for user email lookup	Retrieves logged-in user's email
UserEmail.LDAPFilter	LDAP filter for user search	{0} = sAMAccountName
EmailGroups.LDAPRoot	LDAP path for email groups	Used for action reminders
EmailGroups.LDAPFilter	Filter for reminder groups	Finds groups with "Reminder" in name
ADGroupReader	AD group for read-only access	Full IKEA group path
ADGroupPublisher	AD group for read/write access	Full IKEA group path
ADGroupSuperUser	AD group for admin access	Full IKEA group path
SmtpHost	IKEA SMTP gateway	smtp-gw.ikea.com
SmtpPort	SMTP port	25 (no authentication)
SmtpUsername	SMTP user (not used)	Leave empty
SmtpPassword	SMTP password (not used)	Leave empty

### Step 3: Verify Configuration File Permissions

Ensure configuration files have proper permissions:

```
icacls "C:\inetpub\wwwroot\IkeaDocuScan\appsettings.Local.json" /grant "II
icacls "C:\inetpub\wwwroot\IkeaDocuScan\secrets.encrypted.json" /grant "II
```

### Step 4: Configure Scanned Files Path

1. Verify the network share or local path exists:

```
dir \\fileserver\ScannedDocuments
```

2. Test access as App Pool identity:

```
runas /user:"IIS APPPOOL\IkeaDocuScan" "cmd.exe"
dir \\fileserver\ScannedDocuments
```

3. If access denied, grant permissions on the file server

### Step 5: Review and Adjust Settings

Review these settings in appsettings.Local.json:

Setting	Description	Production Value
IkeaDocuScan:MaxFileSizeBytes	Max upload size	52428800 (50MB)
DocumentSearch:MaxResults	Max search results	1000
ExcelExport:MaximumRowCount	Max Excel rows	50000
ExcelExport:WarningRowCount	Warning threshold	10000
Logging:LogLevel:Default	Logging level	Information
Email:EnableEmailNotifications	Enable emails	true

## File Permissions

### Step 1: Set Application Directory Permissions

```
cd C:\inetpub\wwwroot\IkeaDocuScan
```

```
REM Grant Read & Execute to App Pool
```

```
icacls . /grant "IIS APPPOOL\IkeaDocuScan:(OI)(CI)(RX)"
```

```
REM Grant Write to Logs directory
```

```
icacls logs /grant "IIS APPPOOL\IkeaDocuScan:(OI)(CI)(M)"
```

## Step 2: Create Logs Directory

```
cd C:\inetpub\wwwroot\IkeaDocuScan
```


```
mkdir logs
```

```
icacls logs /grant "IIS APPPOOL\IkeaDocuScan:(OI)(CI)(M)"
```

## Step 3: Set Scanned Files Permissions

### For Local Path:

```
icacls "D:\ScannedDocuments" /grant "IIS APPPOOL\IkeaDocuScan:(OI)(CI)(RX)
```



### For Network Share:

On the file server: 1. Share Permissions: Grant **Read** to IIS APPPOOL\IkeaDocuScan (or domain service account) 2. NTFS Permissions: Grant **Read & Execute** to the same account

### Test Access:

```
runas /user:"IIS APPPOOL\IkeaDocuScan" "cmd.exe"
```

```
dir \\fileserver\ScannedDocuments
```

## Step 4: Restrict Configuration File Access

```
cd C:\inetpub\wwwroot\IkeaDocuScan
```

```
REM Remove inherited permissions
```

```
icacls appsettings.Local.json /inheritance:r
```

```
REM Grant specific access
```

```
icacls appsettings.Local.json /grant "Administrators:(F)"
```

```
icacls appsettings.Local.json /grant "IIS APPPOOL\IkeaDocuScan:(R)"
```

```
REM Same for secrets file if it exists
```

```
icacls secrets.encrypted.json /inheritance:r
```

```
icacls secrets.encrypted.json /grant "Administrators:(F)"
```

```
icacls secrets.encrypted.json /grant "IIS APPPOOL\IkeaDocuScan:(R)"
```

## Windows Authentication Setup

### Step 1: Verify IKEA Active Directory Groups

Ensure the following IKEA AD groups exist and users are properly assigned:

AD Group	Purpose	Access Level
UG-DocScanningReaders-CG@WAL-FIN-CH-GEL	View documents	Read-only
UG-DocScanningPublishers-CG@WAL-FIN-CH-GEL	Create/edit documents	Read/Write
UG-DocScanningSuperUsers-CG@WAL-FIN-CH-GEL	Full admin access	SuperUser

#### Verify Group Membership:

Use Active Directory Users and Computers or PowerShell:

```
# Check if groups exist
Get-ADGroup -Filter "Name -like '*DocScanning*'" | Select-Object Name, Dis

# Check members of a group
Get-ADGroupMember -Identity "UG-DocScanningReaders-CG@WAL-FIN-CH-GEL"
```

## Step 2: Verify LDAP Configuration

The LDAP settings are configured in appsettings.Local.json (Step 2 of Application Configuration).

#### Verify LDAP connectivity:

```
# Test LDAP connection
$domain = "ikea.com"
$ldapPath = "LDAP://DC=ikea,DC=com"

$searcher = New-Object System.DirectoryServices.DirectorySearcher
$searcher.SearchRoot = New-Object System.DirectoryServices.DirectoryEntry(
$searcher.Filter = "(objectClass=user)"
$searcher.PropertiesToLoad.Add("sAMAccountName") | Out-Null
$result = $searcher.FindOne()

if ($result) {
    Write-Host "LDAP connection successful" -ForegroundColor Green
} else {
    Write-Host "LDAP connection failed" -ForegroundColor Red
}
```

## Step 3: Test Windows Authentication

1. Browse to application URL from domain-joined machine
2. Should automatically authenticate with current user
3. If prompted for credentials, check:
  - o IIS Windows Authentication is enabled
  - o Browser is configured for Integrated Windows Authentication
  - o Site is in Intranet zone (IE/Edge)

## Step 4: Grant Initial Admin Access

**To Be Defined:** The process for granting initial SuperUser access to the first administrator will be defined by the development team based on the final user permissions structure.

**Expected Steps:** 1. Identify initial admin user(s) from IKEA 2. Add user(s) to UG-DocScanningSuperUsers-CG@WAL-FIN-CH-GEL AD group 3. Verify user appears in application with SuperUser access after first login



If database seeding is required, development team will provide script.

---

## Post-Deployment Verification

### Step 1: Check Application Pool Status

1. Open IIS Manager
2. Navigate to **Application Pools**
3. Verify **IkeaDocuScan** pool is **Started**
4. If stopped, check Event Viewer for errors

### Step 2: Check Application Logs

1. Navigate to logs directory:

```
cd C:\inetpub\wwwroot\IkeaDocuScan\logs
dir
```

2. Open most recent stdout log file

3. Look for:

- ☐ “Now listening on: http://localhost:5000”
- ☐ “Application started”
- ☐ Any exception stack traces

### Step 3: Check Windows Event Logs

1. Open **Event Viewer**
2. Navigate to **Windows Logs** → **Application**
3. Filter for:
  - Source: **IIS AspNetCore Module V2**
  - Source: **ASP.NET Core**
4. Check for errors or warnings

### Step 4: Test Database Connection

1. Browse to application URL
2. Application should start without errors
3. Check logs for EF Core connection success:

```
Entity Framework Core initialized
Database connection successful
```

### Step 5: Test Application Endpoints

Access these URLs and verify responses:

URL	Expected Result
https://docuscan.company.com	Home page loads
https://docuscan.company.com/health	Returns “Healthy”
https://docuscan.company.com/api/health	Returns JSON health status

### Step 6: Test User Authentication

1. Browse to application from domain-joined machine
2. Verify automatic authentication with Windows credentials
3. Navigate to **Documents** → **Search Documents**

4. Verify access based on AD group membership

### Step 7: Test Document Operations

1. **Search Documents:** Verify search functionality works
2. **View Document:** Click on a document to view details
3. **Check File Access:** Verify scanned files can be accessed
4. **Test Excel Export:** Generate an Excel export from a report

### Step 8: Test Email Notifications (If Enabled)

1. Navigate to a feature that sends emails (e.g., Access Request)
2. Submit a test request
3. Verify email is received
4. Check SMTP logs if email not received

### Step 9: Verify Version Number

Check application version is correct:

1. Browse to application
2. Check browser's Developer Tools → Network tab
3. Look for DLL version in response headers or assembly info

**OR** check file properties:

```
cd C:\inetpub\wwwroot\IkeaDocuScan
powershell "(Get-Item IkeaDocuScan-Web.dll).VersionInfo.FileVersion"
```

### Step 10: Performance Check

Monitor application performance:

1. Open **Performance Monitor** (perfmon)
2. Add counters:
  - ASP.NET Core → Requests/Sec
  - .NET CLR Memory → # Bytes in all Heaps
  - Process → % Processor Time (w3wp)
3. Generate some load and verify metrics are reasonable

---

## Troubleshooting Common Issues

### Issue: Application Pool Stops Immediately

**Symptoms:** - Pool starts but stops after a few seconds - 502.5 error in browser

**Resolution:** 1. Check stdout logs in logs directory 2. Verify .NET 10.0 Runtime installed:  
cmd dotnet --list-runtimes 3. Should show: Microsoft.AspNetCore.App 10.0.x 4. Install ASP.NET Core Hosting Bundle 10.0 if missing

### Issue: Database Connection Fails

**Symptoms:** - 500 error on any database operation - "Cannot open database" in logs - "Login failed for user 'docuscanh'" in logs

**Resolution:** 1. Verify connection string is encrypted in secrets.encrypted.json 2. Test SQL connection with docuscanh user: cmd sqlcmd -S PROD-SQL-01 -d IkeaDocuScan -U docuscanh -P [password] 3. Verify docuscanh user has database access: ""sql USE IkeaDocuScan;

- Check if login exists SELECT name, type\_desc FROM sys.server\_principals WHERE

```
name = 'docuscanch';
```

– Check if user exists in database `SELECT name, type_desc FROM sys.database_principals WHERE name = 'docuscanch';`

– Check user roles `EXEC sp_helpuser 'docuscanch';` 4. If user missing, ensure migration scripts were executed completely 5. Verify password is correct in ConfigEncryptionTool output

### Issue: Windows Authentication Not Working

**Symptoms:** - Prompted for credentials repeatedly - Anonymous user shown in logs

**Resolution:** 1. Verify Anonymous Authentication is **Disabled** in IIS 2. Verify Windows Authentication is **Enabled** 3. Check browser Intranet zone settings 4. Add site to Trusted Sites if needed

### Issue: Cannot Access Scanned Files

**Symptoms:** - Files list is empty - “Access denied” errors

**Resolution:** 1. Verify path in appsettings.Local.json is correct 2. Test access as App Pool identity: `cmd runas /user:"IIS APPPOOL\IkeaDocuScan" "cmd.exe" dir \\fileserver\ScannedDocuments` 3. Grant permissions on file server if access denied

### Issue: DPAPI Decryption Fails

**Symptoms:** - “Unable to decrypt configuration” errors - SMTP or database passwords not working

**Resolution:** 1. Verify secrets.encrypted.json was created using App Pool identity 2. Re-encrypt using ConfigEncryptionTool running as correct user 3. Alternative: Use environment variables instead

### Issue: SignalR Not Working

**Symptoms:** - Real-time updates not working - WebSocket connection failures in browser console

**Resolution:** 1. Verify WebSocket Protocol feature installed in IIS 2. Check Application Request Routing (ARR): IIS Manager → Server → Application Request Routing → Server Proxy Settings Enable proxy: OFF (unless needed) 3. Verify firewall allows WebSocket connections


---

## Rollback Procedure

If deployment fails and rollback is necessary:

### Step 1: Stop Application Pool

```
%systemroot%\system32\inetsrv\appcmd stop apppool /apppool.name:"IkeaDocuS
```



### Step 2: Restore Previous Files

1. Delete current deployment files
2. Copy previous version files from backup
3. Restore appsettings.Local.json from backup

### Step 3: Rollback Database (If Necessary)

If migrations were applied that need reversal:

```
dotnet ef database update <PreviousMigrationName>
```

**OR** restore database backup:

```
USE master;
GO
ALTER DATABASE IkeaDocuScan SET SINGLE_USER WITH ROLLBACK IMMEDIATE;
GO
RESTORE DATABASE IkeaDocuScan FROM DISK = 'C:\Backups\IkeaDocuScan_Backup.
GO
ALTER DATABASE IkeaDocuScan SET MULTI_USER;
GO
```

Step 4: Start Application Pool

```
%systemroot%\system32\inetsrv\appcmd start apppool /apppool.name:"IkeaDocu
```

Step 5: Verify Rollback Success

Test application functionality as per Step 5-8 in Post-Deployment Verification.

Appendix A: Configuration Reference

Required Configuration Sections

Section	Purpose	Required
ConnectionStrings	Database connection	<input type="checkbox"/> Yes
IkeaDocuScan	Application settings	<input type="checkbox"/> Yes
Email	SMTP configuration	<input type="checkbox"/> Yes (if notifications enabled)
ExcelExport	Excel generation settings	<input type="checkbox"/> <input type="checkbox"/> Optional (has defaults)
Logging	Logging configuration	<input type="checkbox"/> <input type="checkbox"/> Optional (has defaults)

Sensitive Settings Checklist

These should be in appsettings.Local.json or secrets.encrypted.json:

- In secrets.encrypted.json (DPAPI-encrypted):** - [ ]  
ConnectionStrings:DefaultConnection (includes docuscan password) - [ ]  
IkeaDocuScan:ScannedFilesPath
- In appsettings.Local.json (server-specific):** - [ ] IkeaDocuScan:DomainName (ikea.com) - [ ] IkeaDocuScan:UserEmail:LDAPRoot - [ ]  
IkeaDocuScan:UserEmail:LDAPFilter - [ ] IkeaDocuScan:EmailGroups:LDAPRoot - [ ]  
IkeaDocuScan:EmailGroups:LDAPFilter - [ ] IkeaDocuScan:ADGroupReader (IKEA group) - [ ] IkeaDocuScan:ADGroupPublisher (IKEA group) - [ ]  
IkeaDocuScan:ADGroupSuperUser (IKEA group) - [ ] Email:SmtpHost (smtp-gw.ikea.com) - [ ] Email:ApplicationUrl (https://docuscan.ikea.com) - [ ]  
ExcelExport:ApplicationUrl (https://docuscan.ikea.com)

Appendix B: Health Check Endpoints

The application includes health check endpoints:

Endpoint	Purpose	Response
/health	Basic health check	“Healthy” (200 OK)
/health/ready	Readiness probe	JSON status
/health/live	Liveness probe	JSON status

Example Response:

```
{
  "status": "Healthy",
  "checks": [
    {
      "name": "Database",
      "status": "Healthy",
      "description": "Connection successful"
    },
    {
      "name": "FileSystem",
      "status": "Healthy",
      "description": "Scanned files accessible"
    }
  ],
  "totalDuration": "00:00:00.1234567"
}
```

Use these endpoints for monitoring and load balancer health checks.

Document Version

Version	Date	Author	Changes
1.0	2025-01-06	System	Initial deployment plan

End of Deployment Plan